

Pilight Overview

Pilight manuals <http://manual.pilight.org/>

Wiki-Seiten

1. [pilight problems](#)
2. [pilight_debug](#)
3. [pilight crontab](#)
4. [pilight script](#)
5. [pilight_configuration_obfelden](#)
6. [pilight](#)
7. [pilight_config.json](#)
8. [pilight_doku](#)

Configuration of switches

Schaltsteckdose

Button 1 "On"

```
pilight-send -t -i 2816 -u 0 -p quigg_gt7000
```

```
{
  "message": {
    "id": 2816,
    "unit": 0,
    "state": "on"
  },
  "origin": "receiver",
  "protocol": "quigg_gt7000",
  "uuid": "0000-b8-27-eb-f2329e",
  "repeats": 1
}
```

Button 1 "Off"

```
pilight-send -f -i 2816 -u 0 -p quigg_gt7000
```

```
{
  "message": {
    "id": 2816,
    "unit": 0,
    "state": "off"
  },
}
```

```
    "origin": "receiver",
    "protocol": "quigg_gt7000",
    "uuid": "0000-b8-27-eb-f2329e",
    "repeats": 1
}
=== Button 2 "On" ===
pilight-send -t -i 2816 -u 1 -p quigg_gt7000
<code>
{
    "message": {
        "id": 2816,
        "unit": 1,
        "state": "on"
    },
    "origin": "receiver",
    "protocol": "quigg_gt7000",
    "uuid": "0000-b8-27-eb-f2329e",
    "repeats": 3
}
```

Button 2 "Off"

```
pilight-send -f -i 2816 -u 1 -p quigg_gt7000
```

```
{
    "message": {
        "id": 2816,
        "unit": 1,
        "state": "off"
    },
    "origin": "receiver",
    "protocol": "quigg_gt7000",
    "uuid": "0000-b8-27-eb-f2329e",
    "repeats": 1
}
```

Button 3 "On"

```
{
    "message": {
        "id": 2816,
        "unit": 2,
        "state": "on"
    },
    "origin": "receiver",
    "protocol": "quigg_gt7000",
    "uuid": "0000-b8-27-eb-f2329e",
    "repeats": 1
}
```

```
}
```

Button 4 "On"

```
{
  "message": {
    "id": 2816,
    "unit": 3,
    "state": "on"
  },
  "origin": "receiver",
  "protocol": "quigg_gt7000",
  "uuid": "0000-b8-27-eb-f2329e",
  "repeats": 1
}
```

Button 4 "Off"

```
{
  "message": {
    "id": 2816,
    "unit": 3,
    "state": "off"
  },
  "origin": "receiver",
  "protocol": "quigg_gt7000",
  "uuid": "0000-b8-27-eb-f2329e",
  "repeats": 1
}
```

Button Master (all) "On"

```
{
  "message": {
    "id": 2816,
    "all": 1,
    "state": "on"
  },
  "origin": "receiver",
  "protocol": "quigg_gt7000",
  "uuid": "0000-b8-27-eb-f2329e",
  "repeats": 1
}
```

HomeEasy

Button 1 "On"

```
pilight-send -t -s 25 -u 11 -p elro_800_switch
```

```
{
  "message": {
    "systemcode": 25,
    "unitcode": 11,
    "state": "on"
  },
  "origin": "receiver",
  "protocol": "elro_800_switch",
  "uuid": "0000-b8-27-eb-f2329e",
  "repeats": 1
}
```

Button 1 "Off"

```
pilight-send -f -s 25 -u 11 -p elro_800_switch
```

```
{
  "message": {
    "systemcode": 25,
    "unitcode": 11,
    "state": "off"
  },
  "origin": "receiver",
  "protocol": "elro_800_switch",
  "uuid": "0000-b8-27-eb-f2329e",
  "repeats": 1
}
```

Button 2 "On"

```
{
  "message": {
    "systemcode": 25,
    "unitcode": 13,
    "state": "on"
  },
  "origin": "receiver",
  "protocol": "elro_800_switch",
  "uuid": "0000-b8-27-eb-f2329e",
  "repeats": 2
}
```

Button 2 "Off"

```
{
  "message": {
    "systemcode": 25,
    "unitcode": 13,
    "state": "off"
  },
  "origin": "receiver",
  "protocol": "elro_800_switch",
  "uuid": "0000-b8-27-eb-f2329e",
  "repeats": 1
}
```

Button Master (all) "On"

```
{
  "message": {
    "systemcode": 25,
    "unitcode": 27,
    "state": "on"
  },
  "origin": "receiver",
  "protocol": "elro_800_switch",
  "uuid": "0000-b8-27-eb-f2329e",
  "repeats": 1
}
```

Button Master (all) "Off"

<code> {

```
  "message": {
    "systemcode": 25,
    "unitcode": 31,
    "state": "off"
  },
  "origin": "receiver",
  "protocol": "elro_800_switch",
  "uuid": "0000-b8-27-eb-f2329e",
  "repeats": 1
}
```

From:

<https://www.huw.moenkeberg.ch/> - **HousAutomation Pi**

Permanent link:

<https://www.huw.moenkeberg.ch/doku.php?id=pilight>

Last update: **2022/01/09 14:41**

